



Informatica® Cloud Data Integration

Microsoft Azure Blob Storage V2 Connector

© Copyright Informatica LLC 2017, 2024

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at <https://www.informatica.com/trademarks.html>. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at <https://www.informatica.com/legal/patents.html>.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2024-05-20

Table of Contents

Chapter 1: Introduction to Microsoft Azure Blob Storage V2 Connector.....	4
Microsoft Azure Blob Storage V2 Connector Overview.	4
Microsoft Azure Blob Storage V2 Connector Task and Object Types.	5
Microsoft Azure Blob Storage V2 Connector Example.	5
Administration of Microsoft Azure Blob Storage V2 Connector.	5
Chapter 2: Connections for Microsoft Azure Blob Storage V2.....	6
Microsoft Azure Blob Storage V2 connections overview.	6
Microsoft Azure Blob Storage V2 connection properties.	6
Chapter 3: Synchronization Tasks with Microsoft Azure Blob Storage V2	8
Microsoft Azure Blob Storage V2 Sources in Synchronization Tasks.	8
Microsoft Azure Blob Storage V2 Targets in Synchronization Tasks.	9
Rules and guidelines for synchronization tasks.	10
Chapter 4: Mappings for Microsoft Azure Blob Storage V2.....	11
Data compression in Microsoft Azure Blob Storage V2 sources and targets.	11
Directory source in Microsoft Azure Blob Storage sources.	12
Microsoft Azure Blob Storage V3 sources in mappings.	13
Microsoft Azure Blob Storage V2 targets in mappings.	14
Specifying a target.	16
Target time stamps.	16
File formatting options.	17
Microsoft Azure Blob Storage V3 target file parameterization.	19
Microsoft Azure Blob Storage V3 target file parameterization through a parameter file.	19
Rules and guidelines for mappings and mapping tasks.	19
Appendix A: Data type reference.....	20
Microsoft Azure Blob Storage V2 and Transformation Data Types.	20
Avro data types and transformation data types.	21
JSON data types and transformation data types.	21
Parquet data types and transformation data types.	22
Index.....	23

CHAPTER 1

Introduction to Microsoft Azure Blob Storage V2 Connector

You can use Microsoft Azure Blob Storage V2 Connector to securely read from or write to Microsoft Azure Blob Storage.

Use Microsoft Azure Blob Storage V2 Connector to read and write delimited files and complex files such as Avro, JSON, and Parquet.

Blobs are files of any type and size, and are organized into containers in Microsoft Azure Storage. You can use a Microsoft Azure Blob Storage V2 connection to access delimited, Avro, and Parquet files that are block blobs or append blobs.

You cannot read and write nested and multi-line indented JSON files.

You can use Microsoft Azure Blob Storage V2 objects as sources and targets in mappings and mapping tasks.

You can switch mappings to advanced mode to include transformations and functions that enable advanced functionality.

Microsoft Azure Blob Storage V2 Connector Overview

Microsoft Azure Blob Storage V2 connector enables you to read delimited data from or write delimited data to blobs in Microsoft Azure Storage. When you write to Microsoft Azure Blob Storage V2, you can insert delimited data to a target object or create a new target object.

Blobs are files of any type and size, and are organized into containers in Microsoft Azure Storage. You can access delimited files that are page blobs, block blobs, or append blobs with Microsoft Azure Blob Storage V2 connections.

When you read delimited data from or write delimited data to Microsoft Azure Blob Storage, you can specify the Hosted Agent or the Secure Agent.

You can switch mappings to advanced mode to include transformations and functions that enable advanced functionality.

Microsoft Azure Blob Storage V2 Connector Task and Object Types

The following table lists the Microsoft Azure Blob Storage V2 object types that you can use in Data Integration tasks:

Task Type	Source	Target	Lookup
Synchronization	Yes	Yes	No
Mapping	Yes	Yes	No

Microsoft Azure Blob Storage V2 Connector Example

You work in sales operations and want to score leads to drive higher sales for your organization. You need to bring in leads from Salesforce to Microsoft Azure Storage. You can score leads for sales readiness in Microsoft Azure Machine Learning, and then load the lead scores back into Salesforce. You can keep data up to date with the latest leads and lead scores by scheduling a task flow to run on a regular basis.

You have leads in Salesforce, with data such as the contact information, industry, company size, and marketing information.

You configure a synchronization task to insert leads from Salesforce to Microsoft Azure Blob Storage V2. Use Microsoft Azure Machine Learning to score the leads, and then create another synchronization task to load the lead scores into Salesforce.

You create a task flow so that the synchronization tasks run serially on a schedule. The sales organization can see the most current lead scores for prospects, and focus on the most promising leads, increasing efficiency.

Administration of Microsoft Azure Blob Storage V2 Connector

Before you use Microsoft Azure Blob Storage V2 objects in tasks, an administrator must perform the following tasks:

- Get the storage account name and account key for Microsoft Azure Blob Storage.
- Create a blob container in Microsoft Azure Blob Storage.

CHAPTER 2

Connections for Microsoft Azure Blob Storage V2

Create a Microsoft Azure Blob Storage V2 connection to securely read data from or write data to Microsoft Azure Blob Storage. You can use a Microsoft Azure Blob Storage V2 connection to specify sources and targets in mappings and mapping tasks.

Microsoft Azure Blob Storage V2 connections overview

Microsoft Azure Blob Storage V2 connection enables you to transfer files from a Microsoft Azure Blob Storage source to a Microsoft Azure Blob Storage target. You can use Microsoft Azure Blob Storage V2 connections to read data from or write data to Microsoft Azure Blob Storage.

Use Microsoft Azure Blob Storage V2 connections to specify sources or targets in a mapping and mapping task.

Create a Microsoft Azure Blob Storage V2 connection on the **Connections** page and associate it with a mapping or mapping task. Define the source and target properties to read or write data to Microsoft Azure Blob Storage.

Microsoft Azure Blob Storage V2 connection properties

When you create a Microsoft Azure Blob Storage V2 connection, you must configure the connection properties.

The following table describes Microsoft Azure Blob Storage V2 connection properties:

Connection property	Description
Runtime Environment	The name of the runtime environment where you want to run the tasks.
Account Name	Microsoft Azure Blob Storage account name.

Connection property	Description
Account Key	Microsoft Azure Blob Storage access key.
Container Name	Microsoft Azure Blob Storage container name.

CHAPTER 3

Synchronization Tasks with Microsoft Azure Blob Storage V2

This chapter includes the following topics:

- [Microsoft Azure Blob Storage V2 Sources in Synchronization Tasks, 8](#)
- [Microsoft Azure Blob Storage V2 Targets in Synchronization Tasks, 9](#)
- [Rules and guidelines for synchronization tasks, 10](#)

Microsoft Azure Blob Storage V2 Sources in Synchronization Tasks

When you create a synchronization task with a Microsoft Azure Blob Storage V2 source, you can configure source properties.

You can configure Microsoft Azure Blob Storage V2 properties on the **Source** page of the Synchronization Task wizard.

The following table describes the Microsoft Azure Blob Storage V2 source properties:

Property	Description
Connection Name	Name of the source connection.
Source Type	Source type. Select Single for a single source object.
Source Object	The Microsoft Azure Blob Storage V2 blob that you want to use as a source object.
Formatting Options	Opens the Formatting Options dialog box to define the format of the file. Configure the following format options: <ul style="list-style-type: none">- Delimiter: Delimiter character. You can configure other parameters such as comma, tab, colon, semicolon, or others.- Text Qualifier: Character to qualify text. You can configure other parameters such as single quote or double quote.- Escape: Escape character.

The following table describes the Microsoft Azure Blob Storage V2 advanced source properties:

Advanced Property	Description
Number of concurrent connections to Blob Store	The number of concurrent connections to Blob Store to download files. Default is 4.
Blob Name Override	Overrides the default file name.
Blob Container Override	Overrides the default container name. Note: When you create a new target at the run time and select the blob container override property, the Secure Agent generates an empty header file in the container specified in the connection.
Header in the first row of Blob	Indicates that the first row of the Blob is a header and the Secure Agent does not read the first row.

Microsoft Azure Blob Storage V2 Targets in Synchronization Tasks

You can insert data to a target or create a new target in Microsoft Azure Blob Storage V2 for synchronization tasks. You can use a single Microsoft Azure Blob Storage V2 object or multiple related Microsoft Azure Blob Storage V2 objects as targets in a synchronization task. When you configure more than one Microsoft Azure Blob Storage V2 target, you can select the parent object and add a child object.

Configure Microsoft Azure Blob Storage V2 target properties on the **Target** page of the synchronization Task wizard.

The following table describes the Microsoft Azure Blob Storage V2 target properties:

Property	Description
Connection	Name of the target connection.
Target Object	Name of the target object.
Formatting Options	Opens the Formatting Options dialog box to define the format of the file. Configure the following format options: <ul style="list-style-type: none">- Delimiter: Delimiter character. You can configure other parameters such as comma, tab, colon, semicolon, or others.- Text Qualifier: Character to qualify text. You can configure other parameters such as single quote or double quote.- Escape: Escape character.

You configure Microsoft Azure Blob Storage V2 advanced target properties on the **Schedule** page of the synchronization Task wizard.

The following table describes the Microsoft Azure Blob Storage V2 advanced target properties:

Advanced Property	Description
Number of concurrent connections to Blob Store	The number of concurrent connections to Blob Store to upload files. Default is 4.
Blob Name Override	Overrides the default file name. You must use this property when you want to write compressed blob files to Microsoft Azure Blob Storage.
Blob Container Override	Overrides the default container name. Note: When you create a new target at the run time and select the blob container override property, the Secure Agent generates an empty header file in the container specified in the connection.
Header in the first row of Blob	Creates a header in the target file. Header will not be created in the target file if this option is not selected.
Compress newly created Blob	Compresses the newly created blob when set to True.
Write Strategy	Appends block to a blob, when you select append blob.
Blob Type	Writes data to a block blob or an append blob.
Success File Directory	NA
Error File Directory	NA

Rules and guidelines for synchronization tasks

Consider the following guidelines when you configure a synchronization task:

- When you run a task to read a Microsoft Azure Blob Storage source, use either comma or pipe as the delimiter.
- The Text Qualifier formatting option is ignored for data preview and at run time in a synchronization task.
- Ensure that the source blob does not contain single quote (') as the text qualifier.
- The **Compress newly created Blob** option is ignored if you do not override the blob.

CHAPTER 4

Mappings for Microsoft Azure Blob Storage V2

When you configure a mapping, you describe the flow of data from the source to the target.

When you create a mapping, you define the Source transformation and Target transformation to represent a Microsoft Azure Blob Storage V2 object. Use the Mapping Designer in Data Integration to add the Source or Target transformations in the mapping canvas and configure the Microsoft Azure Blob Storage V2 source and target properties.

In advanced mode, the Mapping Designer updates the mapping canvas to include transformations and functions that enable advanced functionality.

You can use Monitor to monitor the jobs.

Data compression in Microsoft Azure Blob Storage V2 sources and targets

You can decompress data when you read data from Microsoft Azure Blob Storage and compress the data when you write data to Microsoft Azure Blob Storage.

Configure the compression format in the **Compression Format** option under the advanced source and target properties.

For the Flat resource type, select only the Gzip compression format. The following table lists the compression formats for Avro and Parquet resource types:

Compression format	Avro File	Flat File	JSON File	Parquet File
None	Yes	Yes	Yes	Yes
Deflate*	Yes	N/A	No	No
Gzip	No	Yes	No	Yes
Bzip2	N/A	N/A	No	N/A
Lzo	N/A	N/A	No	N/A

Compression format	Avro File	Flat File	JSON File	Parquet File
Snappy*	Yes	N/A	No	Yes
*Select None to decompress the Deflate and Snappy file formats.				

To read a compressed file from Microsoft Azure Blob Storage, the compressed file must have specific extensions. If the extensions used to read the compressed file are not valid, the Secure Agent does not process the file. The following table describes the extensions that are appended based on the compression format that you use:

Compression format	File Name Extension
Deflate	.deflate
Gzip	.GZ
Bzip2	.BZ2
Lzo	.LZO
Snappy	.snappy

Directory source in Microsoft Azure Blob Storage sources

You can select the type of source from which you want to read data.

You can select the following type of sources from the **Source Type** option under the advanced source properties:

- File
- Directory

Use the following rules and guidelines to select **Directory** as the source type:

- All the source files in the directory must contain the same metadata.
- All the files must have data in the same format. For example, delimiters, header fields, and escape characters must be same.
- All the files under a specified directory are parsed. The files under subdirectories are not parsed.
- The connector does not perform any validation if there are multiple blob formats in the directory you select and might result into errors.

Microsoft Azure Blob Storage V3 sources in mappings

In a mapping, you can configure a Source transformation to represent a Microsoft Azure Blob Storage V3 object.

The following table describes the Microsoft Azure Blob Storage V3 source properties that you can configure in a Source transformation:

Property	Description
Connection	Name of the source connection. Select a source connection or click New Parameter to define a new parameter for the source connection.
Source Type	Source type. Select one of the following types: <ul style="list-style-type: none">- Single Object- Parameter: Select Parameter to define the source type when you configure the mapping task.
Object	Name of the source object. You can drill-down and select an object from a sub-folder to fetch metadata from a particular object. When you run a task, the Secure Agent reads data from the container you specified either in connection properties or in the advance properties.
Parameter	Select an existing parameter for the source object or click New Parameter to define a new parameter for the source object. The Parameter property appears only if you select Parameter as the source type.
Format	Specifies the file format that the Microsoft Azure Blob Storage V3 Connector uses to read data from Microsoft Azure Blob Storage. You can select the following file format types: <ul style="list-style-type: none">- Flat- Avro- Parquet- JSON Default is None . You must select the Format Type as None to read binary files. For more information, see "File formatting options" on page 17 .

The following table describes the Microsoft Azure Blob Storage V3 advanced source properties that you can configure in a Source transformation:

Property	Description
Number of concurrent connections to Blob Store	The number of concurrent connections to Blob Store to upload files. Default is 4.
Source Type	Select the type of source from which you want to read data. You can select the following source types: <ul style="list-style-type: none">- File- Directory Default is File.

Property	Description
Blob Name Override	Overrides the default file name.
Blob Container Override	<p>Overrides the default container name.</p> <p>When you read data from a directory and override the Blob container, ensure that files in the Blob container that you override with are not empty.</p> <p>When you generate the SAS token at the container-level, the default container name and the container name that you specify for the container override must be the same.</p>
Compression Format	<p>Decompresses data when you read data from Microsoft Azure Blob Storage. You can decompress the data in the following formats:</p> <ul style="list-style-type: none"> - None. Select None to decompress deflate and snappy file formats. - Gzip - Bzip2 - Lzo <p>Default is None.</p>
Tracing Level	<p>Sets the amount of detail that appears in the log file.</p> <p>You can choose terse, normal, verbose initialization, or verbose data.</p> <p>Default is normal.</p>

Microsoft Azure Blob Storage V2 targets in mappings

In a mapping, you can configure a Target transformation to represent a Microsoft Azure Blob Storage V2 object.

The following table describes the Microsoft Azure Blob Storage V2 target properties that you can configure in a Target transformation:

Property	Description
Connection	Name of the target connection. Select a target connection or click New Parameter to define a new parameter for the target connection.
Target Type	<p>Target type. Select one of the following types:</p> <ul style="list-style-type: none"> - Single Object. - Parameter. Select Parameter to define the target type when you configure the task.
Object	<p>Name of the target object. You can select an existing object or create a new target at run time.</p> <p>When you select Create New at Runtime, enter a name and path for the target object and select the source fields that you want to use. By default, all source fields are used. The Path attribute is not applicable.</p> <p>The target name can contain alphanumeric characters. You can use only a period (.), an underscore (_), an at the rate sign (@), a dollar sign (\$), and a percentage sign (%) special characters in the file name.</p> <p>You can use parameters defined in a parameter file in the target name.</p>
Parameter	<p>Select an existing parameter for the target object or click New Parameter to define a new parameter for the target object.</p> <p>The Parameter property appears only if you select Parameter as the target type.</p>

Property	Description
Format	<p>Specifies the file format that the Microsoft Azure Blob Storage V3 Connector uses to read data from Microsoft Azure Blob Storage.</p> <p>You can select the following file format types:</p> <ul style="list-style-type: none"> - Flat - Avro - Parquet - JSON <p>Default is None.</p> <p>You must select the Format Type as None to read binary files.</p> <p>For more information, see "File formatting options" on page 17.</p>
Operation	Target operation. Select Insert . You can only insert data to a Microsoft Azure Blob Storage target.

The following table describes the Microsoft Azure Blob Storage V3 advanced target properties that you can configure in a Target transformation:

Property	Description
Number of concurrent connections to Blob Store	The number of concurrent connections to Blob Store to upload files. Default is 4.
Blob Name Override	Overrides the default file name. You must use this property when you want to write compressed blob files to Microsoft Azure Blob Storage.
Blob Container Override	<p>Overrides the default container name.</p> <p>When you create a new target at the run time and select the blob container override property, the Secure Agent generates an empty header file in the container specified in the connection.</p> <p>When you specify the blob container override in the target, ensure that you specify the file that you want to write to the target in the blob name override property.</p> <p>When you generate the SAS token at the container-level, the default container name and the container name that you specify for the container override must be the same.</p>
Compression Format	<p>Compresses data when you write data to Microsoft Azure Blob Storage. You can compress the data in the following formats:</p> <ul style="list-style-type: none"> - None - Deflate - Gzip - Bzip2 - Lzo - Snappy <p>Default is None.</p>
Write Strategy	Appends block to a blob, when you select append blob. Applicable to .csv files only.
Blob Type	Writes data to a block blob or an append blob.
Forward Rejected Rows	Not applicable.

Specifying a target

You can use an existing target or create a target to hold the results of a mapping. If you choose to create the target, the agent creates the target when you run the task.

To specify the target properties, follow these steps:

1. Select the Target transformation in the mapping.
2. On the **Incoming Fields** tab, configure field rules to specify the fields to include in the target.
3. To specify the target, click the **Target** tab.
4. Select the target connection.
5. For the target type, choose **Single Object** or **Parameter**.
6. Specify the target object or parameter.
 - To create a target file at run time, enter the name for the target file including the extension, for example, `Accounts.csv`.
Note: When you read from a flat file, ensure that the file contains some data and not the header alone. If the file has only a header, the header is not written to the target.
 - If you want the file name to include a time stamp, click **Handle Special Characters** and add special characters to the file name. For example, add the special characters shown here to include all the time stamp information: `Accounts_%d%m%y%T.csv`.
Note: The Handle Special Characters option is not applicable to mappings in advanced mode.
7. Click **Formatting Options** if you want to configure the formatting options for the file, and click **OK**.
8. Click **Select** and choose a target object. You can select an existing target object or create a new target object at run time and specify the object name.
9. Specify Advanced properties for the target, if needed.

Target time stamps

When you create a target at run time in a mapping, you can append time stamp information to the file name to show when the file is created.

When you specify the file name for the target file, include special characters based on Linux STRFTIME function formats that the mapping task uses to include time stamp information in the file name. The time stamp is based on the organization's time zone.

You cannot append time stamp information to the file name for mappings in advanced mode.

The following table describes some common STRFTIME function formats that you might use in a mapping or mapping task:

Special Character	Description
%d	Day as a two-decimal number, with a range of 01-31.
%m	Month as a two-decimal number, with a range of 01-12.
%y	Year as a two-decimal number without the century, with range of 00-99.
%Y	Year including the century, for example 2015.
%T	Applicable only to flat files. Time in 24-hour notation, equivalent to %H:%M:%S.

Special Character	Description
%H	Hour in 24-hour clock notation, with a range of 00-24.
%I	Hour in 12-hour clock notation, with a range of 01-12.
%M	Minute as a decimal, with a range of 00-59.
%S	Second as a decimal, with a range of 00-60.
%p	Either AM or PM.

Note: For complex files, instead of %T you can use the equivalent %H_%M_%S.

File formatting options

When you select the format of a Microsoft Azure Blob Storage file, you can configure the formatting options.

The following table describes the formatting options for Avro, Parquet, JSON, and delimited flat files:

Property	Description
Schema Source	The schema of the source or target file. Select one of the following options to specify a schema: <ul style="list-style-type: none"> - Read from data file. Imports the schema from the file in Microsoft Azure Blob Storage. - Import from schema file. Imports schema from a schema definition file in your local machine.
Schema File	The schema definition file in the agent machine from where you want to upload the schema. You cannot upload a schema file when you select the Create Target option.

The following table describes the formatting options for flat files:

Property	Description
Flat File Type	The type of flat file. Select one of the following options: <ul style="list-style-type: none"> - Delimited. Reads a flat file that contains column delimiters. - Fixed Width. Not applicable.
Delimiter	Character used to separate columns of data. You can set values as comma, tab, colon, semicolon, or others. You can't set a tab as a delimiter directly in the Delimiter field. To set a tab as a delimiter, you must type the tab character in any text editor. Then, copy the character to the Delimiter field.
EscapeChar	Character immediately preceding a column delimiter character embedded in an unquoted string, or immediately preceding the quote character in a quoted string.

Property	Description
Qualifier	Quote character that defines the boundaries of text strings. You can configure parameters such as single quote or double quote. You can use the output text qualifier when a delimiter value is present in the data.
Qualifier Mode	Specify the qualifier behavior for the target object. You can select one of the following options: <ul style="list-style-type: none"> - Minimal. Default mode. Applies qualifier to data enclosed within a delimiter value or a special character. - All. Applies qualifier to all data.
Code Page	Select the code page that the Secure Agent must use to read or write data. Microsoft Azure Blob Storage V3 Connector supports only UTF-8. Ignore rest of the code pages.
Header Line Number	Specify the line number that you want to use as the header when you read data from Microsoft Azure Blob Storage. You can also read a data from a file that does not have a header. To read data from a file with no header, specify the value of the Header Line Number field as 0.
First Data Row	Specify the line number from where you want to start reading the data. Enter a value greater than or equal to one. To read data from the header, the value of the Header Line Number and the First Data Row fields should be the same. Default is 1.
Target Header	Select whether you want to write data to a target that contains a header or without a header in the flat file. You can select With Header or Without Header options. This property is not applicable when you read data from a Microsoft Azure Blob Storage V3 source.
Distribution Column	Not applicable.
escapeCharacterDataRetained	Not applicable.
maxRowsToPreview	Not applicable.
rowDelimiter	Not applicable.

The following table describes the formatting options for JSON files:

Property	Description
Data elements to sample	Not applicable.
Memory available to process data	Not applicable.

Microsoft Azure Blob Storage V3 target file parameterization

When you parameterize the file name and target folder location for Microsoft Azure Blob Storage V3 target objects, you can pass the file name and folder location at run time. If the folder does not exist, the Secure Agent creates the folder structure dynamically.

Microsoft Azure Blob Storage V3 target file parameterization through a parameter file

You can parameterize a Microsoft Azure Blob Storage V3 target file using a parameter file.

To parameterize a Microsoft Azure Blob Storage V3 target file using a parameter file, create a Microsoft Azure Blob Storage V3 target object and add parameters in the target object name and target object path. Define the parameter that you added for the target object in the parameter file. Then, place the parameter file in the following location and run the mapping task:

```
<Informatica Cloud Secure Agent\apps\Data_Integration_Server\data\userparameters>
```

Rules and guidelines for mappings and mapping tasks

Consider the following rules and guidelines when you configure mappings and mapping tasks:

- When you edit the metadata, all native data types change to Bigint and you cannot change the scale and precision of data types except for the string data type.
- When you write a JSON file to Microsoft Azure Data Lake Blob Storage, ensure that the column names do not contain unicode characters.
- Ensure that the scale of a double data type is not set to 0 in the target file when you read data from or write data to Microsoft Azure Blob Storage.
- The data preview and mapping fail if you read an Avro file that contains binary fields.
- Ensure that the field names in the source or target object do not contain special characters or unicode characters.
- You cannot preview data when you read or write a compressed file.
- When you write an Avro or a Parquet file, ensure that the file does not contain null values, else incorrect data is written in the target for the fields with null values.
- You cannot select append blob as blob type when you read or write a JSON file.

APPENDIX A

Data type reference

Data Integration uses the following data types in Microsoft Azure Blob Storage V3 mappings and mapping tasks:

- Microsoft Azure Blob Storage V3 native data types appear in the source and target transformations when you choose to edit metadata for the fields.
- Transformation data types. Set of data types that appear in the transformations. These are internal data types based on ANSI SQL-92 generic data types, which the Secure Agent uses to move data across platforms. They appear in all transformations in a mapping.

When the Secure Agent reads source data, it converts the native data types to the comparable transformation data types before transforming the data. When the Secure Agent writes to a target, it converts the transformation data types to the comparable native data types.

Microsoft Azure Blob Storage V2 and Transformation Data Types

The following table lists the Microsoft Azure Blob Storage V2 data types that the Secure Agent supports and the corresponding transformation data types:

Microsoft Azure Blob Storage V2 Native Data Type	Transformation Data Type	Range and Description
String	String	1 to 104,857,600 characters

Avro data types and transformation data types

Avro file data types map to transformation data types that the Secure Agent uses to move data across platforms.

The following table lists the Avro file data types that the Secure Agent supports and the corresponding transformation data types:

Avro Data Type	Transformation Data Type	Range and Description
Boolean	Integer	TRUE (1) or FALSE (0)
Bytes	Binary	Precision 4000
Double	Double	Precision 15
Float	Double	Precision 15
Int	Integer	-2,147,483,648 to 2,147,483,647 Precision 10, scale 0
Long	Bigint	-9,223,372,036,854,775,808 to 9,223,372,036,854,775,807 Precision 19, scale 0
Null	Integer	-2,147,483,648 to 2,147,483,647 Precision 10, scale 0
String	String	-1 to 104,857,600 characters

JSON data types and transformation data types

JSON complex file data types map to transformation data types that the Secure Agent uses to move data across platforms.

The following table lists the JSON complex file data types that the Data Integration supports and the corresponding transformation data types:

JSON Data Type	Transformation Data Type	Range and Description
boolean	integer	The default transformation type for boolean is integer. You can specify string data type with values of True and False. True is equivalent to the integer 1 and False is equivalent to the integer 0.
Number (double)	double	-1.79769313486231570E+308 to +1.79769313486231570E+308. Precision 15.

JSON Data Type	Transformation Data Type	Range and Description
Number (float)	double	-1.79769313486231570E+308 to +1.79769313486231570E+308. Precision 15.
Number (int)	integer	-2,147,483,648 to 2,147,483,647 Precision 10, scale 0
Number (long)	bigint	-9,223,372,036,854,775,808 to 9,223,372,036,854,775,807 Precision 19, scale 0.
string	string	1 to 104,857,600 characters.

Parquet data types and transformation data types

Parquet file data types map to transformation data types that the Secure Agent uses to move data across platforms.

The following table lists the Parquet file data types that the Secure Agent supports and the corresponding transformation data types:

Parquet Data Type	Transformation Data Type	Range and Description
Boolean	Integer	TRUE (1) or FALSE (0)
Byte_Array	Binary	Arbitrarily long byte array
Double	Double	Precision 15
Float	Double	Precision 15
Int32	Integer	-2,147,483,648 to +2,147,483,647
Int64	Bigint	-9,223,372,036,854,775,808 to +9,223,372,036,854,775,807 8-byte signed integer
Int96	Binary	12-byte signed integer

The Parquet schema that you specify to read or write a Parquet file must be in smaller case. Parquet does not support case-sensitive schema.

INDEX

A

- administration [5](#)
- advanced source properties in Synchronization tasks [8](#)
- advanced target properties Synchronization tasks [9](#)

B

- blobs [4](#)

C

- complex file format JSON [21](#)
- connections Microsoft Azure Blob Storage V2 [6](#)
- create target
 - adding time stamps [16](#)
 - target file parameterization [16](#), [19](#)

D

- data compression
 - sources and targets [11](#)
- data type reference
 - overview [20](#)
- data types
 - avro [21](#)
 - parquet [22](#)
- directory source
 - Microsoft Azure Blob Storage sources [12](#)

E

- error file directory [9](#)
- error files [5](#)

F

- files
 - delimited [4](#)

M

- mappings
 - target properties [14](#)
 - source properties [13](#)

- maximum page size [8](#)
- Microsoft Azure Blob Storage connection
 - overview [6](#)
- Microsoft Azure Blob Storage V2
 - connection properties [6](#)
- Microsoft Azure Blob Storage V3 Connector
 - overview [4](#)

O

- operations
 - insert [9](#)
- overview [4](#)

P

- parameterization through a parameter file [19](#)

S

- sorted ports [8](#)
- Source transformation
 - Microsoft Azure Blob Storage properties [13](#)
- sources
 - in Synchronization tasks [8](#)
- sources in mappings [13](#)
- specifying targets [16](#)
- success file directory [9](#)
- success files [5](#)
- Synchronization tasks
 - sources [8](#)

T

- target objects
 - multiple [9](#)
- Target transformation
 - Microsoft Azure Blob Storage properties [14](#)
- targets
 - Synchronization tasks [9](#)
- targets in mappings [14](#)
- tracing level [13](#)